

Olympus P-400 Printing

PREPPING YOUR IMAGE FILES

Preparing an Image File for printing with the Olympus P-400 - either Felix or Oscar

- 1) In Photoshop CS3, create a copy of your edited image file.
- 2) Your file should be in RGB mode(Image-->Mode Menu). Ideally your file would have an AdobeRGB profile(also in the Image-->Mode-->Convert Profile Menu)
- 3) Use Image Size (in the Image Menu) to adjust your document to the size you want to print it.
 - a) Maximum paper size is A4 and printable area is 7.64 in. x 10 in.
 - b) Ideal resolutions for the Olympus P-400 is 314 dpi. For optimal print quality, resize your image to 314 dpi in Photoshop.
- 4) Flatten your image. The "Flatten Image" action is found at the bottom of the "Layer" Menu.
- 5) Save your file.

PRINTING YOUR IMAGES

Use Photoshop CS3 to print. You will navigate three separate windows during the printing process.

Print Window - (Adobe)

- 1) From the File Menu choose "Print"
- 2) The "Print" window appears. Click the "Page Setup..." button.

Page Setup Window

- 3) The "Page Setup" window appears.
 - a) Click on the "Format for:" pop-up button. Choose "Felix P400" or "Oscar P400".
 - b) Click on the "Paper Size:" pop-up button. Choose A4.
 - c) From the "Orientation" section, choose Portrait (image more vertical) or Landscape (image more horizontal)
 - d) Leave "Scale:" at 100%.
 - e) Click the "OK" button.
 - f) The "Page Setup" window closes and takes you back to the Print window.

Print Window - (Adobe)

- 4) Your image should now fit within the preview pane in the upper left corner of the "Print" window. If not you have chosen a paper size that is too small or an incorrect orientation. Return to the "Page Setup" window.
- 5) See Color Management handout for details on using ICC profiles.
- 6) Click the "Print..." button.

Print Window - (Apple)

- 7) The Photoshop "Print" window closes and the standard Apple "Print" window appears.
 - a) Click on the "Printer" pop-up button. Choose "Felix P400" or "Oscar P400".
 - b) Click the "Print" button at the lower right hand corner of the window.

Your image should now print. The paper will

To check the printing status, open Print Setup Utility and double-click Felix P400 or Oscar P400.